



KOMPACT STAIR CONFIGURATOR

STEP-BY-STEP INSTRUCTIONS

Our Products: Eureka Phoenix Karina **Kompact** Railings Genius

Kompact Adjustable Staircase Kit

Total Flexibility. 152 Possible Configurations.

Covered by a worldwide patent, **Kompact** is the only staircase with adjustable rise, going, height, depth and rotation. Its total flexibility allows endless configurations, with 1 or 2 one quarter turns (L or U) to fit any space. Click [here](#) to download a PDF file detailing the many ways the **Kompact** can be configured. The Kit comes with 13 risers (12 treads) and internal railing. The going is adjustable between **7 and 8 inches** and between **8 and 10 inches** depending on configurations. The riser is adjustable between **6 and 9 inches**.

Try the Kompact Configurator
Lay out a Kompact stair kit to your specifications!

[Click here to get started](#)

Please Note: the measurement values on the configuration tables are reflected in inches and eighths of inches. For example, 75.3 inches = 75 3/8 inches. Also note that the configurator opens in a pop-up window. If you have a pop-up blocker enabled you will need to disable or make an exception for this site.

With the purchase of one or more tread kits you can reach a height of **146 inches**. The treads are clear sealed solid beech with metal supports and matching balusters and accessories. The handrail is solid beech. In place of a knee or half wall along your top floor or opening, [balcony rail kits](#) of identical materials and finish are available to complete the contemporary appearance of your staircase.

STEP 1:
Select Product

STEP 2:
Click here to begin Kompact Stair Configurator.

arke Welcome to the configurator **Kompact**
Select the chosen plan and click **heights** to configure your staircase

1 plans ▶ 2 heights ▶ 3 project ▶ 4 colours ▶ 5 printing

STEP 3:
Follow instructions.



KOMPACT STAIR CONFIGURATOR

STEP-BY-STEP INSTRUCTIONS

arke what height must go over your **Kompact**

Height in **INCHES** from finished floor to finished floor

landing floor

starting floor

114.2

Ceiling thickness in **INCHES**

11.8

1 plans ▶ 2 heights ▶ 3 project ▶ 4 colours ▶ 5 printing

STEP 4:
Enter height in inches.

STEP 5:
Enter ceiling thickness in inches.

STEP 6:
Click on "Project" to go to the next step.

arke Personalize your **Kompact**

landing floor

starting floor

98.4

44.9

53.6

Here is your stair. In order to show a wall or a balustrade presence, click around the ceiling opening until the required object will appear.

Choose your stair model:

- The cheapest
- The smallest
- The biggest
- The most comfortable

Stair details:

model Kompact 89 L

tread number 12

rise number 13

height 114.2 in

ceiling opening thickness 1.8 in

tread width 35 in

tread going 8.7 in

final going 13 in

tread height 8.8 in

head room 85.5 in

stair components:

Q.ty	Description	Codes
1	Kit Kompact 89 L Grey	35025

1 plans ▶ 2 heights ▶ 3 project ▶ 4 colours ▶ 5 printing

update project

NOTE:
1 - Here a window appears to let you know that by clicking on the black or grey lines you are able to add or delete walls or railings.
Black line = Railing
Grey line = Wall
2 - Click on "X" to close window.



KOMPACT STAIR CONFIGURATOR

STEP-BY-STEP INSTRUCTIONS

Personalize your Kompact

Choose your stair model:

- The cheapest
- The smallest
- The biggest
- The most comfortable

Stair details:

model Kompact 89 L
 tread number 12
 rise number 13
 height 114.2 in
 ceiling opening thickness 1.8 in
 tread width 35 in
 tread going 8.7 in
 final going 13 in
 tread height 8.8 in
 head room 85.5 in

stair components:

Q.ty	Description	Codes
1	Kit Kompact 89 L Grey	35025

1 plans 2 heights 3 project 4 colours 5 printing update project

STEP 7:
Enter opening measurements here.

STEP 8:
Click on "Colours" to go to next step.

Personalize your Kompact

choose the colour of your stair

Stair details:

model Kompact 89 L
 tread number 12
 rise number 13
 height 114.2 inc
 ceiling opening thickness 1.8 inc
 tread width 35 inc
 tread going 8.7 inc
 final going 13 inc
 tread height 8.8 inc
 head room 85.5 inc

stair components:

Q.ty	Description	Codes
1	Kit Kompact 89 L Grey	35025

1 plans 2 heights 3 project 4 colours 5 printing save project

This page enables you to see the stair specifications per measurements entered.



KOMPACT STAIR CONFIGURATOR

STEP-BY-STEP INSTRUCTIONS

Personalize your Kompact

choose the colour of your stair

Stair details:

- model Kompact 89 L
- tread number 12
- rise number 13
- height 114.2 inc
- ceiling opening thickness 1.8 inc
- tread width 35 inc
- tread going 8.7 inc
- final going 13 inc
- tread height 8.8 inc
- head room 85.5 inc

stair components:

Q.ty	Description	Codes
1	Kit Kompact 89 L Grey	35025

1 plans 2 heights 3 project 4 colours 5 printing save project

STEP 9:
 1 - If all information is correct you may click on "Printing" to print a copy.
 2 - If information is NOT correct then you may start over.

Personalize your Kompact

choose the colour of your stair

Stair details:

- model Kompact 89 L
- tread number 12
- rise number 13
- height 114.2 inc
- ceiling opening thickness 1.8 inc
- tread width 35 inc
- tread going 8.7 inc
- final going 13 inc
- tread height 8.8 inc
- head room 85.5 inc

stair components:

Q.ty	Description	Codes
1	Kit Kompact 89 L Grey	35025

Attention!

do you wish to print the stair project?

The information and the drawings present in the print will help you while purchasing.

ok cancel

1 plans 2 heights 3 project 4 colours 5 printing save project

Here you will be asked if you are sure you want to print.



KOMPACT STAIR CONFIGURATOR

STEP-BY-STEP INSTRUCTIONS

Sample drawing.pdf - Adobe Acrobat Pro

File Edit View Document Comments Forms Tools Advanced Window Help

arke Your stair characteristics: Kompact 89 L
www.arke.us

landing floor

starting floor

n. treads	n. rises	height	ceiling opening	width	adjustable going	adjustable rise	head room
12	13	114.2	11.8	35	8.7	8.8	85.5

measures in Inches

IN ORDER TO INSTALL YOUR STAIR YOU HAVE TO BUY THE FOLLOWING KITS:

Description	quantity	Codes
Kit Kompact 89 L Grey (RAL 9006)	1	35025

start | Inbox - Micr... | Kompact pr... | Configurato... | * ARKE' IN... | Document1 ... | Sample dra... | 1:05 PM

This is the actual print out you will see if you print.